foreword

This tutorial is to install JDK 8 version on Windows 64-bit platform.

1. install JDK 8

Official website download address:

https://www.oracle.com/java/technologies/downloads/#java8-windows

Step1: Select the JDK version.

Select Java 8 version here:

Java SE subscribers have more choices

Also available for development, personal use, and to run other licensed Oracle products.



Java SE Development Kit 8u321

Java SE subscribers will receive JDK 8 updates until at least December of 2030.

The Oracle JDK 8 license changed in April 2019

The Oracle Technology Network License Agreement for Oracle Java SE is substantially different from prior Oracle JDK 8 licenses. This license permits certain uses, such as personal use and development use, at no cost -- but other uses authorized under prior Oracle JDK licenses may no longer be available. Please review the terms carefully before downloading and using this product. FAQs are available here.

Commercial license and support are available for a low cost with Java SE Subscription.

Step2: Select the system platform

Linux macOS Solaris Wi	ndows	
Product/file description	File size	Download
x86 Installer	157.99 MB	₫ jdk-8u321-windows-i586.exe
x64 Installer	171.09 MB	jdk-8u321-windows-x64.exe

[Note] Download the account that needs to log in to oracle. If not, register one directly.

Step3: Download the installation package

Download completed installation package:



Step4: Start the installation



此版本的 JDK 不再包括 Java Mission Control (JMC) 的副本。JMC 现在需要单独下载。 有关更多信息,请访问 https://www.oracle.com/javase/jmc

> 在我们的安装过程中,不会收集个人信息。 有关我们所收集信息的详细信息



Set the installation path of public JRE: (It is recommended to install jdk1.8.0_321 in the same path as before, that is, under D:\Program Files\Java).

[Note] The public JRE may not be installed.



设置JRE的安装路径,可自定义修改



At this point, JDK8 was successfully installed.

The installed directory is as follows:



Next, you need to configure it.

2. Configure JDK 8

Step1: Configure "environment variable path"

C:\WINDOWS\system32\cmd.exe

```
Microsoft Windows [版本 10.0.17763.864]
(c) 2018 Microsoft Corporation。保留所有权利。
C:\Users\CW>javac
'javac' 不是内部或外部命令,也不是可运行的程序
或批处理文件。
```


[reason for configuring path]

Use win+R shortcut key, open the running window, enter cmd, and enter the cmd program window. If you enter javac, the system prompts that you do not recognize this command.

The reason is that when the input command (program) is executed in the cmd window, the system will first look for the program in the current directory. If it cannot be found, the system will go to the directory specified in an existing environment variable named path in the system to look for the program. If you still can't find it at this step, the error indicated in the above figure will appear.

Therefore, if the directory we are in is the directory where the javac program is located, the javac command (program) will be executed in the cmd window, so that no error will be reported and the program can be executed normally.

For example:



Successfully execute javac program:


```
Microsoft Windows [版本 10.0.17763.864]
c) 2018 Microsoft Corporation。保留所有权利。
D:\Program Files\Java\jdk1.8.0_321\bin><mark>j</mark>avac
用法: javac <options> <source files>
其中,可能的选项包括:
  -g: {lines, vars, source}
  -nowarn
                                                  译器正在执行的操作的消息
过时的 API 的源位置
用户类文件和注释处理程序的
用户类文件和注释处理程序的
  -verbose
  -deprecation
   -classpath 〈路径〉
-cp 〈路径〉
   -sourcepath〈路径
  -bootclasspath 〈路径〉
-extdirs 〈目录〉
  -endorseddirs <目录>
  -proc: {none, on1y}
                                                                         处理程序的名称,绕过默认的搜索进程
  -processor <class1>[, <class2>,
-processorpath <路径> }
   implicit: {none, class}
```

Therefore, in order to execute programs such as javac in any path, it is necessary to configure "environment variable path".

Configuration process:

My computer-properties-advanced system settings-environment variables;


Under system variable: create a new environment variable named "JAVA HOME".



[Note] The path D: $\$ program files $\$ Java $\$ JDK1.8.0 $\$ 321 is the path where I installed JDK8 before.



3. Click to select the Path environment variable, click Edit, and add "%JAVA_HOME%\bin". [Note] Note that there are Path environment variables in both user variables and system variables. The difference between them is that the user variable is only for the currently logged-in user, while the system variable is applicable to all users. Therefore, when modifying the Path environment variable, it is recommended to modify the Path in the system variable directly.



编辑环境变量
X

